

This guide provides instructions to GLOBODOX Server installation and DB Engine Utility installation.

TABLE OF CONTENTS

TABLE OF CONTENTS	1
GLOBODOX SERVER Installation	2
Install MS SQL Server Express Edition using GLOBODOX DB Engine utility	5

GLOBODOX SERVER Installation

1. Go to <https://www.globodox.com/download/>
2. Click on the '**DOWNLOAD**' button for Windows Desktop Client and you will be redirected to the Download Trial page.
3. Fill in the details and click on the Submit button.
4. A file named '**gdxsetup.exe**' will be downloaded.
5. Double click the '**gdxsetup.exe**' setup file to run it. The '**GLOBODOX Setup Wizard**' will be launched. Click Next.



6. On the '**License Agreement**' Page select I accept the agreement. Click Next.


☒ I accept the agreement
☐ I do not accept the agreement

7. The '**GLOBODOX Installation Type**' window will appear. Choose '**Single User Installation or Server Installation**' option. Click Next.

☒ **Single User Installation or Server Installation**
Select this option to install GLOBODOX for a single user.

You must also select this option if you wish to later configure this installation to act as the Server for a multi-machine installation.

8. The '**GLOBODOX Server**' page will appear.
Under the '**Communication Port**' option, It is recommended to use the default port '**(5511)**' used by GLOBODOX server for incoming client connections. However, you can use any communication port of your own. Proceed ahead with the setup by clicking Next.



Communication Port


GLOBODOX Server will listen on this port for incoming GLOBODOX client connections.

Windows Firewall Configuration

☒ Automatic
Select this option to let this setup automatically add an exception to Windows firewall.

☐ Manual
Select this option if you want to manually add the exception to Windows Firewall.


9. On the '**Select Destination Location**' page specify the folder where the setup needs to be installed and click Next.



Setup will install Globodox into the following folder.


To continue, click Next. If you would like to select a different folder, click Browse.

10. The '**GLOBODOX Data Folder Location**' page will appear. Specify the path for GLOBODOX Data Folder and click Next.



Specify the path for the GLOBODOX Data Folder:

11. The '**Select Additional Tasks**' Window will be launched, select the options according to your preferences and Click Next.




Additional shortcuts:


☒ Create a desktop shortcut

☐ Create a Quick Launch icon


12. Click on '**INSTALL**' on the Ready to Install page.



13. The installation will start.



14. Click '**Finish**' to exit the installation setup and start GLOBODOX.



NOTE: In case you face any issues when downloading the file, please contact support@globodox.com or raise a [support ticket](#).

Install MS SQL Server Express Edition using GLOBODOX DB Engine utility

1. Please download the GLOBODOX DB Engine utility from the link below...

For Windows 64 bit:

<http://downloads.globodox.com/dbengine/latest/gdx-db-engine-package-sqle-x64.exe>

For Windows 32 bit:

<http://downloads.globodox.com/dbengine/latest/gdx-db-engine-package-sqle-x86.exe>

2. Run the **gdx-db-engine-package-sqle-x64.exe** (or **gdx-db-engine-package-sqle-x86.exe**) file you downloaded. The '**Globodox DB Engine Installer**' will be launched.
3. Enter your email id and click the Start button.

This can take more than 10 minutes...

-If installation succeeds...

You will see a message which says "**DB Engine installation completed successfully**".

-If installation fails...

If the installation fails, please click OK to send us the log files to investigate the issue.

If installation prompts for restart before the installation completes...

Please restart the machine. On restart, the Globodox DB Engine Installer will launch automatically and continue with the installation...